


OPEN-CUBE QUICK START GUIDE


For more information please visit: open-cube.fel.cvut.cz

Switch ON the Open-Cube and connect it to the computer via USB-B (look for COMport number in the device manager)

1. Use Thonny software to create and debug Micropython programs (select Raspberry Pi PICO as a platform and the right COMport, go to Tools/Options/Interpreter...)
2. See the next page for a list of most common commands, check the full description of available functions on following pages for more detailed information and useful tips.
3. Alternatively, pair the Open-Cube via Bluetooth serial with your computer, use the plug-in to the Thonny program and upload programs wirelessly, see section 3.9 in the more detailed instructions (3.9.4).



***a long press (>5s) of the Power button turns the Open-Cube OFF (secured by hardware circuit, will work even if firmware is corrupted)**



*** the LED is active during charging and turns off when charging is complete or suspended**

LIST OF MOST USEFUL MICROPYTHON O-C COMMANDS

TIMING

```
from time import sleep , sleep_ms , sleep_us
sleep(1)           # Sleep program for 1 second
sleep_ms(2)        # Sleep program for 2 miliseconds
sleep_us(3)        # Sleep program for 3 microseconds look also for "Timer"
```

MOTORS (the same for NXT and EV3), more in chapter 7

```
from lib. robot__consts import Port      # import constants
robot.init__motor(Port.M1)               # initialize the motor
robot.init__motor(Port.M2)               # initialize the motor
robot.motors[Port.M1].set__power(50)     # set power to 50%, clock-wise
robot.motors[Port.M2].set__power(-20)    # set power to 20%, counter-clock-wise
```

SENSORS

NXT TOUCH

```
from lib. robot__consts import Sensor, Port      # import constants, sensor types...
robot.init__sensor(sensor__type = Sensor.NXT__TOUCH, port = Port.S1) # init the sensor on port S1
touch__pressed = robot.sensors.touch[Port.S1].pressed() #read the state of the button
```

NXT OPTICAL see chapter 4.2 for more functions!

```
from lib. robot__consts import Sensor, Port      # import constants, sensor types...
robot.init__sensor(sensor__type = Sensor.LIGHT, port = Port.S1)    # init optical sensor at port S1
robot.sensors.light[Port.S1].on() #switch on the LED
light__intensity = robot.sensors.light[Port.S1].intensity() # measure the light intensity
```

NXT MICROPHONE

```
from lib. robot__consts import Sensor, Port      # import constants, sensor types...
robot.init__sensor(sensor__type = Sensor.NXT__SOUND, port = Port.S1) # init the sensor on port S1
sound__intensity = robot.sensors.sound[Port.S1].intensity() # read the sound intensity
```

NXT ULTRASONIC

```
from lib. robot__consts import Sensor      # import constants, sensor types...
robot.init__sensor(sensor__type = Sensor.NXT__ULTRASONIC) # initialize the sensor
distance = robot.sensors.ultra__nxt.distance() # measure distance
```

NXT GYROSCOPE - currently not implemented (I2C interface, manufactured by HiTechnic)

EV3 TOUCH

```
from lib. robot__consts import Sensor, Port      # import constants, sensor types...
robot.init__sensor(sensor__type = Sensor.EV3__TOUCH, port = Port.S1)    # initialize the sensor
touch__pressed = robot.sensors.touch[Port.S1].pressed() #read the state of the button
```

EV3 OPTICAL see chapter 5.2 for more functions (color sensing for example)

```
from lib. robot__consts import Sensor, Port      # import constants, sensor types...
robot.init__sensor(sensor__type = Sensor.EV3__COLOR, port = Port.S1)    # initialize the sensor
reflection = robot.sensors.light[Port.S1].reflection() # measure the light intensity
```

EV3 ULTRASONIC

```
from lib. robot__consts import Sensor, Port      # import constants, sensor types...
robot.init__sensor(sensor__type = Sensor.EV3__ULTRA, port = Port.S1)    # initialize the sensor
distance = robot.sensors.ultrasonic[Port.S1].distance() # measure the distance
```

EV3 GYROSCOPE *(single axis)*

```
from lib.robot__consts import Sensor, Port          # import constants, sensor types...
robot.init__sensor(sensor__type = Sensor.EV3__GYRO, port = Port.S1)      # initialize the sensor
robot.sensors.gyro[Port.S1].reset__angle(0)         # reset angle
(angle, speed) = robot.sensors.gyro[Port.S1].angle__and__speed()  # measure the angular velocity
in one axis and position
```

O-C OPTICAL *see chapter 6.1 for other modes (color sensing, blue and green light - make POLICE car beacon effect...)*

```
from lib.robot__consts import Sensor, Port          # import constants, sensor types...
robot.init__sensor(sensor__type = Sensor.OC__COLOR, port = Port.S1)      # initialize the sensor
reflection = robot.sensors.light[Port.S1].reflection()  # measure the reflected red light intensity
```

O-C LASER *see chapter 6.2*

```
from lib.robot__consts import Sensor, Port          # import constants, sensor types...
robot.init__sensor(sensor__type = Sensor.OC__LASER, port = Port.S1)      # initialize the sensor
distance = robot.sensors.laser[Port.S1].distance()    # measure the distance
```

O-C ULTRASONIC *see chapter 6.3*

```
from lib.robot__consts import Sensor, Port          # import constants, sensor types...
robot.init__sensor(sensor__type = Sensor.OC__ULTRASONIC, port = Port.S1) # initialize the sensor
distance = robot.sensors.ultrasonic[Port.S1].distance()  # measure the distance
```

O-C AHRS *see chapter 6.4*

```
from lib.robot__consts import Sensor, Port          # import constants, sensor types...
robot.init__sensor(sensor__type = Sensor.OC__GYRO, port = Port.S1)      # initialize the sensor
euler__angles = robot.sensors.gyro[Port.S1].euler__angles()  # read the data (more and calibration
in chapter 6.4)
```

INTERNAL GYROSCOPE *see chapter 3.6 for example of sensor readout using interrupts*

```
robot.init__sensor(sensor__type = Sensor.GYRO__ACC)
a__g__data = (0, 0, 0, 0, 0, 0)          # ax:-, ay:-, az:-, gx:°/s, gy:°/s, gz:°/s
a__g__data = robot.sensors.gyro__acc.read__value()  # measure the accelerations and angular rates
```

MISCELLANEOUS

DISPLAY *see chapter 3.5 for complete list of functions*

```
robot.display.fill(0)          # clear display
robot.display.text("test message",0,0,1)      # print text
x, y = 1.23, 56.789            # set some variables
robot.display.text(f"x={x:.2 f}, y: {y:.2f}", 0, 10, 1)  # print two float numbers
robot.display.show()           # show the framebuffer
```

SOUND - PIEZO

```
robot.buzzer.set__freq__duty(4000,50)         # 4000 Hz, 50 % duty
robot.buzzer.off()                             # stop the PWM generation
```

BUTTONS

```
from lib. robot__consts import Button          # import constants, sensor types...
buttons = robot.buttons.pressed()              # read the state
if buttons[Button.LEFT]: break                 # use it in an if condition
# other buttons: Button.LEFT, Button.RIGHT, Button.OK, Button.UP, Button.DOWN
```

LED *(red, on the Open-Cube front panel)*

```
robot.led.on()          # switch LED on
robot.led.off()          # switch LED off
```

BATTERY

voltage = robot.battery.voltage() *#read the internal O-C Li-ion battery voltage*

I2C MASTER, I2C SLAVE (Open-Cube control, or general usage), see chapter 3.7 and 3.8

BLUETOOTH serial communication & **Wi-Fi** access point – see chapter 3.7

MicroPython also supports:

```
if x < 9:    while x < 9:    for y in range(0, 9):
print("debug message!")    # print debug message into Thonny console
def add(number1, number2):    return number1 + number2    # function definition
add(1, 2)    # function usage

send__data = 0.1    #create some variable
buffer = "Values: " + str(send__data) + "," + str(-send__data) + ";"    # Values: 0.1,-0.1;
print(buffer)    #Print the string to PC
or
robot.esp.bt__write(buffer)    # or send it via Bluetooth
```

Want to see **time-plots** of some variables? Look for "*DataPlotter*"

<https://github.com/jirimaier/DataPlotter> nice program created by CTU-FEE student Jiri Maier

```
buffer = "$$P"+str(send__data)+"," +str(-send__data)+";"
```

```
robot.esp.bt__write(buffer)    #more info in bt_serial.py in your Open-Cube or at gitlab
```

"\$\$P" is a specific header to add one point into a graph, see *DataPlotter* documentation

Open-Cube

CTU FEE

2024

Contents

1	Firmware installation	4
2	Thonny IDE	4
2.1	Recommended settings	4
2.2	Uploading code to the cube	4
2.3	Run the program independently	5
3	Robot	6
3.1	Buttons	8
3.2	LED	9
3.3	Buzzer	9
3.4	Battery	10
3.5	Display	11
3.6	Gyroscope and accelerometer	15
3.7	I2C master	17
3.8	I2C slave	19
3.9	ESP32 communication	20
3.9.1	Bluetooth ESP32 connection with external device	20
3.9.2	Cube	23
3.9.3	Remote control of the cube	26
3.9.4	Wireless program launch	27
3.9.5	Serial Bluetooth Terminal	27
3.9.6	Matlab	27
3.9.7	Simulink	28
4	NXT sensors	32
4.1	Touch sensor	32
4.2	Light sensor	32
4.3	Ultrasonic sensor	34
4.4	Sound sensor	35

5	EV3 sensors	36
5.1	Touch sensor	36
5.2	Color sensor	36
5.3	Ultrasonic sensor	38
5.4	Infrared sensor	38
5.5	Gyroscopic sensor	39
6	Open-Cube sensors	41
6.1	Color sensor	41
6.2	Laser distance sensor	43
6.3	Ultrasonic sensor	44
6.4	AHRS sensor	44
7	Motor	46
8	Parameters and constants	49
8.1	Sensor	49
8.2	Port	50
8.3	Button	50
8.4	Light	51
8.5	GyroAcc	51
8.6	Color	52
9	Useful MicroPython functions	53
9.1	Information printing	53
9.2	Random number generation	53
9.3	Time	54
9.4	Binary data manipulation	55
9.5	Multi-core programming	55
10	Used Python terms	56

List of codes

1	Run the program independently.	5
2	Using the global robot variable.	7
3	Checking the status of the buttons.	8
4	LED usage.	9
5	Buzzer usage.	10
6	Determining battery voltage.	10
7	Display usage.	14
8	Getting raw data and cube orientation from gyroscope and accelerometer.	16
9	Using the cube for multi-cube communication as an I2C master.	18
10	Using the cube for multi-cube communication as an I2C slave.	19
11	Communication between the micro controller and ESP32.	25
12	Communication with the cube using Matlab.	27
13	NXT Touch Sensor usage.	32
14	NXT Light Sensor usage.	34
15	NXT Ultrasonic Sensor usage.	34
16	NXT Sound Sensor usage.	35
17	EV3 Touch Sensor usage.	36
18	EV3 Color Sensor usage.	37
19	EV3 Ultrasonic sensor usage.	38
20	EV3 Infrared Sensor usage.	39
21	EV3 Gyro Sensor usage.	40
22	Open-Cube Color Sensor usage.	42
23	Open-Cube LIDAR usage.	43
24	Open-Cube Ultrasonic sensor usage.	44
25	Open-Cube AHRS sensor usage.	45
26	Motor usage.	48
27	Printing information.	53
28	Random library usage.	53
29	Time library usage.	54
30	Timer class usage.	54
31	Struct library usage.	55
32	_thread library usage.	55

1 Firmware installation

The MicroPython firmware, along with all the Open-Cube libraries described in this document, is loaded in the cube by default for students. The current firmware can also be downloaded at [Open-Cube repository](https://gitlab.fel.cvut.cz/open-cube/firmware/) [<https://gitlab.fel.cvut.cz/open-cube/firmware/>] from the micropython folder. To upload firmware after an update, or to upload firmware to a new cube, follow these steps:

1. Download [firmware](https://gitlab.fel.cvut.cz/open-cube/firmware/-/tree/main/micropython/) [<https://gitlab.fel.cvut.cz/open-cube/firmware/-/tree/main/micropython/>] (uf2 binary file) with Open-Cube firmware.
2. Connect the cube to the computer using a USB cable.
3. Hold the boot select button and press the power button.
4. Open the RPI-RP2 directory on your computer and copy the downloaded firmware into it.
5. After uploading the firmware, the cube restarts, the display shows the menu.

2 Thonny IDE

For editing, debugging and uploading code to the cube, we recommend using the [Thonny IDE](https://thonny.org/) [<https://thonny.org/>], which is available for Windows, Mac and Linux.

2.1 Recommended settings

When the editor is started for the first time with the cube connected and running, click the button in the bottom right corner, then click on **Configure interpreter...**, choose **Interpreter** and set the interpreter to **MicroPython (Raspberry Pi Pico)**. It is also recommended to choose **General** and set the option **UI mode** to **regular** or **expert**. In the main Thonny window click on **View** and choose **Files** and **Shell**. The **Files** window is used to browse directories on the computer and the **Shell** window is used to communicate with the cube, display information and error messages.

2.2 Uploading code to the cube

After connecting the switched on cube with a USB cable to the computer, press the **Stop/Restart backend** button in the editor to connect to the cube. The **Shell** box will display the connection information and the **Files** box will display the files loaded in the cube. You can copy files and entire directories between the cube and the computer by right-clicking a file or a directory. Similarly, you can delete or create new files and directories.

You can edit files in both the computer directory and the cube directory. If you open a file in the cube and save it after editing, it will automatically be loaded into the cube.

Upload user programs to the **programs** directory in the cube. A program can be a single file with the **.py** extension, or a directory containing a user file **main.py**. Programs uploaded in this way will appear in the cube menu. The displayed program name is

determined by the name of the file without the `.py` extension or the name of the directory containing `main.py` file.

After editing the code in the editor, you can press **Run current script** to run the code currently displayed in the editor on the cube. It is recommended to run only the main program `main.py` in this way, which contains the cube framework with all the necessary functions for controlling the peripherals initialized. When the main program is run, a menu controlled by the buttons on the cube is displayed with the option to run the loaded user program. The `main.py` file runs automatically when the cube is turned on.

2.3 Run the program independently

To speed up testing, the user program can be run independently without starting the main program:

```
1 # Importing the Robot class
2 from lib.robot import *
3
4 # If the program is run from the menu, nothing happens
5 # If it is run independently, the robot variable is initialized
6 global robot
7 try:
8     robot
9 except:
10     robot = Robot()
11 .
12 .
13 .
14 # When the program exits, the cube can be reset to return to the menu
15 import machine
16 machine.reset()
```

Code 1: Run the program independently.

3 Robot

When the cube is turned on, main program `main.py` initialises a global object `robot`. This object contains all functions for initializing, deinitializing and accessing cube peripheral objects. The functions are described in the following sections. The structure of the variables of the `robot` object that can be used to access the peripheral objects is as follows:

```
robot
├── battery
├── buttons
├── buzzer
├── display
├── esp
├── led
├── motors[4]
├── sensors
│   ├── ultra_nxt
│   ├── gyro_acc
│   ├── touch[4]
│   ├── light[4]
│   ├── sound[4]
│   ├── ultrasonic[4]
│   ├── gyro[4]
│   ├── infrared[4]
│   └── laser[4]
```

`class Robot()`

Initialization, deinitialization and management of motor, sensor and cube peripheral objects. Automatically initializes cube buttons, LED, buzzer and battery voltage measurement with undervoltage protection. Sensors, motors and ESP32 Bluetooth communication can be initialized by the user.

Initialization: Turning on the cube.

Deinitialization: Turning off the cube.

Access: `robot`

```
init_sensor(sensor_type=None, port=None)
```

Sensor initialization.

Parameters: **sensor_type** ([Sensor](#)) – Sensor type.

port ([Port](#)) – Sensor port. No need to specify for sensor types [Sensor.GYRO](#) and [Sensor.ULTRA](#).

```
deinit_sensor(sensor_type=None, port=None)
```

Sensor deinitialization.

Parameters: **sensor_type** ([Sensor](#)) – Sensor type. If not specified, deinitializes any sensor on that port.

port ([Port](#)) – Sensor port. If not specified, deinitializes all sensors of given type.

init_motor(*port=None*)

Motor initialization.

Parameters: **port** ([Port](#)) – Motor port.

deinit_motor(*port=None*)

Motor deinitialization. Shuts down the controller, encoder capture, and stops the motor.

Parameters: **port** ([Port](#)) – Motor port.

The following code demonstrates the use of the robot class on a simple program for flashing the cube LED. When this program is run from the menu, the LED changes state periodically every second. When the left button is pressed, the program is terminated, the display shows the menu again, and you can start another program.

```
1 # Import sleep function
2 from time import sleep
3 # Import cube button constants
4 from lib.robot_consts import Button
5
6 # Program definition
7 def main:
8     # Access the global variable robot
9     global robot
10
11     # Loop waiting for program termination
12     while True:
13         # Change LED state
14         robot.led.toggle()
15
16         # Get buttons state
17         buttons = robot.buttons.pressed()
18         # Terminate program when left button is pressed
19         if buttons[Button.LEFT]:
20             break
21
22         # Wait 1 second
23         sleep(1)
24
25 # Start program
26 main()
```

Code 2: Using the global robot variable.

3.1 Buttons

class Buttons()

Information about the state of the buttons on the front panel of the cube. If the cube does not turn itself off after briefly pressing the POWER button, it can be turned off by long pressing this button to disconnect the cube from the power supply.

Initialization: Turning on the cube.

Deinitialization: Turning off the cube.

Access: robot.buttons

pressed()

Returns current state of the buttons. To find out the status of a specific button, you can use [buttons constants](#).

Returns: Tuple of states of the buttons (power, left, right, ok, up, down). True if the button is pressed, False if not.

Type: (bool, bool, bool, bool, bool, bool)

```
1 # Import sleep function
2 from time import sleep
3 # Import cube button constants
4 from lib.robot_consts import Button
5
6 def main:
7     global robot
8     while True:
9         # Get buttons state
10        buttons = robot.buttons.pressed()
11
12        # Show buttons state in terminal
13        print("Button pressed:",
14              "power:", buttons[Button.POWER],
15              "left:",  buttons[Button.LEFT],
16              "right:", buttons[Button.RIGHT],
17              "OK:",     buttons[Button.OK],
18              "up:",     buttons[Button.UP],
19              "down:",   buttons[Button.DOWN])
20        # Terminate program when left button is pressed
21        if buttons[Button.LEFT]:
22            break
23        # Wait 1 second
24        sleep(1)
25
26 # Start program
27 main()
```

Code 3: Checking the status of the buttons.

3.2 LED

```
class Led()
```

Switching on and off the red LED on the front panel of the cube.

Initialization: Turning on the cube.

Deinitialization: Turning off the cube.

Access: `robot.led`

```
on()
```

Turn on LED.

```
off()
```

Turn off LED.

```
toggle()
```

Change LED state.

```
1 # Turn on LED
2 robot.led.on()
3 # Turn off LED
4 robot.led.off()
```

Code 4: LED usage.

3.3 Buzzer

```
class Buzzer()
```

Controlling the cube buzzer. The buzzer has the highest volume at a frequency of approximately 4500 Hz due to the uneven frequency characteristic of the piezo transducer. The volume can be further adjusted by turning the resistive trimmer on the front panel of the cube.

Initialization: Turning on the cube.

Deinitialization: Turning off the cube.

Access: `robot.buzzer`

```
set_freq_duty(freq, duty)
```

Set the PWM controlling the buzzer to the desired frequency and duty cycle.

- Parameters:**
- **freq** (frekvence: Hz) – PWM frequency.
 - **duty** (střída:%) – PWM duty cycle.

```
off()
```

Turn off buzzer.

```

1 # Turning on the buzzer at 4000 Hz and 50% duty cycle
2 robot.buzzer.set_freq_duty(4000, 50)
3 # Change buzzer frequency to 1000 Hz
4 robot.buzzer.set_freq_duty(1000, 50)
5 # Turn off buzzer
6 robot.buzzer.off()

```

Code 5: Buzzer usage.

3.4 Battery

class Battery()

Voltage measurement on the power supply batteries. During initialization, a timer is set with a 200 ms period to start the voltage measurement.

The Open-Cube is powered by two Li-ion batteries (nominal voltage of one cell is 3.7 V, maximum charging voltage is 4.2 V, discharging below 3 V already shortens the cell lifetime). In case of full charge, 8.2–8.4 V can be measured. Batteries should not be discharged below 6 V. The firmware switches off the cube when voltage drops below 6.5 V. Hardware undervoltage protection disconnects batteries when voltage drops below 5.8 V.

Initialization: Turning on the cube.

Deinitialization: Turning off the cube.

Access: robot.battery

voltage()

Returns the last measured battery voltage.

Returns: Last measured battery voltage.

Type: float: V

read_voltage()

Measure battery voltage.

Returns: Measured battery voltage.

Type: float: V

deinit()

Disable periodic battery voltage measurement.

```

1 # Determine battery voltage in volts
2 voltage = robot.battery.voltage()

```

Code 6: Determining battery voltage.

3.5 Display

```
class SH1106_I2C()
```

Show text, geometric shapes and graphs on the display. The activation of individual pixels is written to the frame buffer, which is transferred to the display using the `show` command. The display is black and white and the resolution is 128x64 pixels.

Initialization: Turning on the cube.

Deinitialization: Turning off the cube.

Access: `robot.display`.

```
show()
```

Show current frame buffer on the display.

```
fill(color)
```

Fill entire frame buffer with specified color.

Parameters: `color` (0/1) – Color – 0 black, 1 white.

```
pixel(x, y [, color])
```

Set a pixel in the frame buffer to the specified color. If color is not specified, returns the color of pixel.

Parameters: • `x`, `y` – Pixel coordinates.
• `color` (0/1) – Color – 0 black, 1 white.

Returns: Pixel color.

Type: int (0/1)

```
hline(x, y, w, color)
```

Draw horizontal line to the frame buffer.

Parameters: • `x`, `y` – Coordinates of left origin of the line
• `w` – Line width.
• `color` (0/1) – Color – 0 black, 1 white.

```
vline(x, y, h, color)
```

Draw vertical line to the frame buffer.

Parameters: • `x`, `y` – Coordinates of upper origin of the line.
• `h` – Line height.
• `color` (0/1) – Color – 0 black, 1 white.

```
line(x1, y1, x2, y2, color)
```

Draw line to the frame buffer.

- Parameters:**
- **x1, y1** – Coordinates of first origin of the line.
 - **x2, y2** – Coordinates of second origin of the line.
 - **color** (0/1) – Color – 0 black, 1 white.

rect(*x, y, w, h, color*)

Draw rectangle to the frame buffer.

- Parameters:**
- **x, y** – Coordinates of the upper left corner of the rectangle.
 - **w, h** – Rectangle width and height.
 - **color** (0/1) – Color – 0 black, 1 white.

fill_rect(*x, y, w, h, color*)

Draw filled rectangle to the frame buffer.

- Parameters:**
- **x, y** – Coordinates of the upper left corner of the rectangle.
 - **w, h** – Rectangle width and height.
 - **color** (0/1) – Color – 0 black, 1 white.

ellipse(*x, y, xr, yr, color, f=False, m=1111b*)

Draw ellipse to the frame buffer.

- Parameters:**
- **x, y** – Coordinates of center of the ellipse.
 - **xr, yr** – Ellipse axes length.
 - **color** (0/1) – Color – 0 black, 1 white.
 - **f** (bool) – Fill the ellipse if the parameter is specified and is True.
 - **m** (4 bits) – Restriction of ellipse drawing to specified quadrants. Bit 0 specifies Q1, b1 Q2, b2 Q3 and b3 Q4. Quadrants are numbered counterclockwise and Q1 is the upper right quadrant.

fill_rect(*x1, y1, x2, y2, x3, y3, color*)

Draw filled triangle to the frame buffer.

- Parameters:**
- **x1, y1, x2, y2, x3, y3** – Coordinates of triangle corners.
 - **color** (0/1) – Color – 0 black, 1 white.

text(*s, x, y, color=1*)

Draw text to the frame buffer. Characters are 8x8 pixels in size. Only one font is available.

- Parameters:**
- **s** (str) – Text.
 - **x, y** – Coordinates of the upper left corner of the text beginning.
 - **color** (0/1) – Color – 0 black, 1 white.

centered_text(*s, y, color=1*)

Draw centered text to the frame buffer. Characters are 8x8 pixels in size. Only one font is available.

- Parameters:**
- **s** (str) – Text.
 - **x** – Coordinate of the upper border of the text.
 - **color** (0/1) – Color – 0 black, 1 white.

```
draw_bar_chart_v(value, x, y, w, h, low_lim=0, high_lim=100,  
no_of_tics=5, label=None, redraw=False)
```

Draw vertical bar chart to the frame buffer.

- Returns:** Redraw chart to reduce flickering.
Type: bool
- Parameters:**
- **value** (float) – Displayed value.
 - **x, y** (int) – Coordinates of the lower left corner of the beginning of the bar chart.
 - **w, h** (int) – Bar chart width and height.
 - **low_lim, high_lim** (int) – Lower and upper constraints of the bar chart.
 - **no_of_tics** (int) – Number of chart divisions for better readability. Recommended maximum value is 5
 - **label** (str) – Chart label.
 - **redraw** (bool) – Chart redraw.

```
draw_bar_chart_h(value, x, y, w, h, low_lim=0, high_lim=100,  
no_of_tics=5, label=None, redraw=False)
```

Draw horizontal bar chart to the frame buffer.

- Returns:** Redraw chart to reduce flickering.
Type: bool
- Parameters:**
- **value** (float) – Displayed value.
 - **x, y** (int) – Coordinates of the lower left corner of the beginning of the bar chart.
 - **w, h** (int) – Bar chart width and height.
 - **low_lim, high_lim** (int) – Lower and upper constraints of the bar chart.
 - **no_of_tics** (int) – Number of chart divisions for better readability. Recommended maximum value is 5
 - **label** (str) – Chart label.
 - **redraw** (bool) – Chart redraw.

```
draw_dial(value, x, y, r, loval, hival, no_of_steps, label, redraw)
```

Draw dial to the frame buffer.

Returns: Redraw dial to reduce flickering.
Type: bool
Parameters:

- **value** (float) – Displayed value.
- **x, y** (int) – Dial center coordinates.
- **r** (int) – Dial radius.
- **loval, hival** (int) – Lower and upper constraints of the dial.
- **no_of_steps** (int) – Number of dial divisions. Recommended maximum value is 10.
- **label** (str) – Dial label.
- **redraw** (bool) – Dial redraw.

continuous_graph(*x, y, gx, gy, w, h, xlo, xhi, ylo, yhi, label, redraw*)

Draw continuous graph to the frame buffer. The function internally maintains graph data points. When the width of the graph is filled, the previous data points are removed and the graph is redrawn from the beginning.

Returns: Redraw chart to reduce flickering.
Type: bool
Parameters:

- **x, y** (float) – Data point to be shown.
- **gx, gy** (int) – Coordinates of the lower left corner of the graph.
- **w, h** (int) – Graph width and height.
- **xlo, xhi** (int) – Lower and upper constraints of the x axis.
- **ylo, yhi** (int) – Lower and upper constraints of the y axis.
- **label** (str) – Graph label.
- **redraw** (bool) – Graph redraw.

```

1 # Delete frame buffer
2 robot.display.fill(0)
3 # Draw text to the upper left corner of the frame buffer
4 robot.display.text("test message", 0, 0, 1)
5
6 # Writing numbers with precision of 2 decimal places to the frame
  buffer on the next line
7 x, y = 1.23, 56.789
8 robot.display.text(f"x={x:.2f}, y: {y:.2f}", 0, 10, 1)
9 # Show frame buffer on the display
10 robot.display.show()
11
12 # Functions that return redraw value to reduce graph flicker should be
  called in the loop as follows
13 redraw = True
14 while(True):
15     redraw = robot.display.draw_dial(50,128/2,40,20,0,100,10,270,
      "Speedometer",redraw)

```

Code 7: Display usage.

3.6 Gyroscope and accelerometer

```
class ICM42688()
```

Integrated gyroscope and accelerometer ICM42688.

Measurement of acceleration and angular velocity in three axes. Sensor data fusion to obtain cube orientation – Euler angles and quaternions.

Initialization: `robot.init_sensor(sensor_type=Sensor.GYRO_ACC)`

Deinitialization: `robot.deinit_sensor(sensor_type=Sensor.GYRO_ACC)`

Access: `robot.sensors.gyro_acc`

```
raw()
```

Returns the last measured angular velocity and acceleration values. The [GyroAcc](#) constants of the gyroscope and accelerometer can be used to find a specific value.

Returns: Tuple of accelerations and angular velocities in the x, y, z axes.

Type: (a_x: -, a_y: -, a_z: -, g_x: °/s, g_y: °/s, g_z: °/s)

```
euler_angles()
```

Returns the orientation of the cube in Euler angles. The fusion algorithm must be on.

Returns: Tuple of Euler angles yaw, pitch roll.

Type: (yaw: °, pitch: °, roll: °)

```
quaternions()
```

Returns the orientation of the cube in quaternions. The fusion algorithm must be on.

Returns: Tuple of quaternions.

Type: (w, x, y, z)

```
start_fusion()
```

Turns on the accelerometer and gyroscope data fusion algorithm to obtain Euler angles and quaternions.

```
stop_fusion()
```

Turns off the accelerometer and gyroscope data fusion algorithm.

```
reset_fusion()
```

Resets the current cube orientation (Euler angles are zero and quaternion is identity).




Figure 1: Orientation of integrated gyroscope and accelerometer axes.

Example of getting raw data and cube orientation from gyroscope and accelerometer:

```

1 # Importing libraries
2 from time import sleep
3 # Importing constants
4 from lib.robot_consts import Button, Sensor, GyroAcc
5
6 # Initializing sensor and data fusion algorithm
7 robot.init_sensor(sensor_type=Sensor.GYRO_ACC)
8 robot.sensors.gyro_acc.start_fusion()
9
10 # Loop waiting for the program to exit
11 while True:
12     # Display the last acceleration and angular velocity values
13     a_g_data = robot.sensors.gyro_acc.raw()
14     print("Acc:",
15           a_g_data[GyroAcc.AX],
16           a_g_data[GyroAcc.AY],
17           a_g_data[GyroAcc.AZ],
18           "Gyro:",
19           a_g_data[GyroAcc.GX],
20           a_g_data[GyroAcc.GY],
21           a_g_data[GyroAcc.GZ])
22
23     # Display the orientation of the cube
24     euler_angles = robot.sensors.gyro_acc.euler_angles()
25     print("Yaw:", euler_angles[0],
26           "Pitch:", euler_angles[1],
27           "Roll:", euler_angles[2])
28
29     # Get button state
30     buttons = robot.buttons.pressed()
31     # Exit the program if the left button is pressed
32     if buttons[Button.LEFT]:
33         break
34     # Put the program to sleep for 1 second
35     sleep(1)
36

```

```

37 # Deinitialize sensor
38 robot.deinit_sensor(sensor_type=Sensor.GYRO_ACC)

```

Code 8: Getting raw data and cube orientation from gyroscope and accelerometer.

3.7 I2C master

```
class I2C_master()
```

Set the cube as I2C master device for multi-cube communication. Cubes can be connected using the I2C port (NXT UTZ port) and a modified cable. For proper operation one cube must be set as I2C master and the others as I2C slave. The I2C master reads or writes data to the 252 I2C slave registers.

Initialization: `robot.init_i2c_master()`
Deinitialization: `robot.deinit_i2c_master()`
Access: `robot.i2c_master`

```
read(slave_add, len=1, mem_add=None)
```

Read data from I2C slave device.

Parameters: **slave_add** (8-119) – Address of the I2C slave device.
len (int) – Number of registers (bytes) to read.
mem_add (0-252) – Register address to read. If None, it is read from the last address read or written.
Returns: Data from I2C slave device.
Type: bytes

```
write(slave_add, message, mem_add=None)
```

Writes data to the I2C slave device.

Parameters: **slave_add** (8-119) – Address of the I2C slave device.
message (bytes) – Data to be written.
mem_add (0-252) – Address of the register to read. If None, writes from the last read or written address.
Returns: True if writing is successful, False if not.
Type: bool

```
trigger(time_us, slave_add, callback=None)
```

Sets the wake-up time for the I2C slave device. The I2C slave must have a callback function set in advance.

Parameters: **time_us** (int) – Time (us) after which the set callback function will be called.
slave_add (8-119) – Address of the I2C slave device.
callback (callable) – Callback function that is called in the I2C master device after the specified time has elapsed.
Returns: True if the setting is successful, False if not.
Type: bool

`trigger_all(time_us, slave_adds=None, callback=None)`

Sets the wake-up of several I2C slave devices. I2C slaves must have callback functions set in advance.

Parameters: `time_us` (int) – Time (us) after which the set callback function will be called.

`slave_adds` (list) – List of I2C slave device addresses. If None, performs an I2C bus scan and sets the trigger for all devices found.

`callback` (callable) – Callback function that is called in the I2C master device after the specified time has elapsed.

Returns: True if the setting is successful, False if not (for example, if the selected time for calling the callback function is too short).

Type: bool

`scan()`

Performs a scan of the I2C bus.

Returns: A list of I2C slave device addresses available on the I2C bus.

Type: list

```
1 # Initialize the cube as an I2C master
2 robot.init_i2c_master()
3
4 # Scan the I2C bus to obtain all I2C slave device addresses
5 all_adds = robot.i2c_master.scan()
6
7 # Write and read the character "a" (97) to the I2C slave device with
  address 10 in register 1
8 robot.i2c_master.write(10, (97).to_bytes(1, 'little'), mem_add=1)
9 data_read = robot.i2c_master.read(10, 1, mem_add=1)
10 print(chr(int.from_bytes(data_read, 'little'))) # "a"
11
12 # Callback function for synchronization between cubes
13 def master_trigger_callback(timer):
14     robot.led.on()
15
16 # Set trigger in all found I2C slave devices in 1 s (1000000 us)
17 robot.i2c_master.trigger_all(1000000, slave_adds=all_adds, callback=
  master_trigger_callback)
18
19 # Deinitialize I2C master
20 robot.deinit_i2c_master()
```

Code 9: Using the cube for multi-cube communication as an I2C master.

3.8 I2C slave

`class I2C_slave()`

Set the cube as an I2C slave device for multi-cube communication. Cubes can be connected using the I2C port (NXT UTZ port) and a modified cable. For proper operation one cube must be set as I2C master and the others as I2C slave. The I2C master reads or writes data to the 252 I2C slave registers.

The address of the I2C slave device can be selected in the range 7-119.

Initialization: `robot.init_i2c_slave(address)`

Deinitialization: `robot.deinit_i2c_slave()`

Access: `robot.i2c_slave`

`read(mem_add)`

Reads the register.

Parameters: **mem_add** (0-251) – Address of the register to read.

Returns: Data from the register.

Type: int

`read_all()`

Reads all registers.

Returns: List with data from registers.

Type: list

`write(mem_add, data)`

Writes to the register.

Parameters: **mem_add** (0-251) – Address of the register to write to.

data (0-255) – Data to write.

`irq(handler=None, trigger=0)`

Sets the interrupt handler function.

Parameters: **handler** (callable) – Callback function, must have one input argument for the I2C_slave instance.

trigger (0-7) – Event mask at which the handler function is called.

`robot.i2c_slave.RECEIVED` – I2C master wrote data to the register.

`robot.i2c_slave.READ` – I2C master read data from the register.

`robot.i2c_slave.TRIGGER` – I2C master trigger.

```
1 # Initialize the cube as an I2C slave with address 10
2 robot.init_i2c_slave(10)
3
4 # Callback function for responding to events
5 def slave_callback(i2c_slave):
```



```

6  flags = i2c_slave.irq().flags()
7  if (flags & i2c_slave.RECEIVED):
8      print("new data received")
9  if (flags & i2c_slave.READ):
10     print("master read data")
11  if (flags & i2c_slave.TRIGGER):
12     robot.led.on()
13
14  # Set interrupt handler for all three possible events
15  flags = robot.i2c_slave.RECEIVED | robot.i2c_slave.READ | robot.
    i2c_slave.TRIGGER
16  robot.i2c_slave.irq(handler=slave_callback, trigger=flags)
17
18  # Write and read the character "b" (98) to register 2
19  robot.i2c_slave.write(2, 98)
20  data_received = robot.i2c_slave.read(2)
21  print(chr(data_received)) # "b"
22
23  # Deinitialize I2C slave
24  robot.deinit_i2c_slave()

```

Code 10: Using the cube for multi-cube communication as an I2C slave.

3.9 ESP32 communication

ESP32 communicates with the cube (RP2040) via serial link. It can communicate with other devices via Wi-Fi or Bluetooth. The ESP is programmable by connecting a USB cable on the top of the cube. The default firmware of the ESP (available from the [Open-Cube repository](https://gitlab.fel.cvut.cz/open-cube/firmware/-/tree/main/ESP) [<https://gitlab.fel.cvut.cz/open-cube/firmware/-/tree/main/ESP>]) allows in Bluetooth mode to forward data from the cube via Bluetooth virtual COM port to a computer or mobile phone and in Wi-Fi mode acts as an access point with a web server with versatile controls (buttons, switches, indicators).

3.9.1 Bluetooth ESP32 connection with external device

Communication is serial via Bluetooth virtual COM port and has been tested for Windows, Ubuntu, and Android. To pair, the cube must be turned on in the BT pair menu. The device name will appear on the display.

- Windows:
 1. In the Bluetooth settings, select Add new device, then Bluetooth, and pair the computer with the cube. See figure 2.
 2. Confirm the PIN on the cube and on the computer.
 3. To find the COM port number, go to the advanced Bluetooth settings. The required COM port has a name containing ESP32SPP and the direction Outgoing. See figure 3. This COM port is used for both receiving and sending data.
- Ubuntu:
 1. In the Bluetooth settings, select the Open-Cube device and pair the computer with the cube.

2. Confirm the PIN on the cube and on the computer.
 3. Display the device details and copy its MAC address.
 4. Create a serial port link: `sudo rfcomm bind /dev/rfcomm0 XX:XX:XX:XX:XX:XX`.
 5. Open the serial port, for example, with the command `screen /dev/rfcomm0`
- Android:
 1. In the Bluetooth settings, select the Open-Cube device and pair your phone with the cube.
 2. Confirm the PIN on the cube and on your phone.




Figure 2: Pairing with cube on Windows.




Figure 3: Determining the COM port number

3.9.2 Cube

`class ESP()`

Bidirectional data sending between microcontroller and ESP32 via UART interface. At initialization, a timer with a 10 ms period is started, during which the data sent by the ESP is received and stored.

ESP can operate in two modes – Bluetooth and Wi-Fi access point.

1. In the case of Bluetooth mode, data is sent in messages. Sending and receiving data can be done in ASCII or in binary mode.

ASCII mode: The message being sent is terminated by the LF (new line) terminator. When receiving data, the message is available after receiving the LF or CR terminator.

Binary mode: For communication, it is necessary to specify the header of the data being sent and received to distinguish the beginning of the message. In order to correctly receive the message and determine the end of the message, the size of the message in bytes must be pre-specified. The data is of type bytes and its interpretation is up to the user.

2. Wi-Fi access point mode with web server provides versatile controls – buttons, switches and indicators.

Initialization: Turning on the cube.

Deinitialization: Turning off the cube.

Access: `robot.esp`

`reset()`

Reset the ESP and set Bluetooth mode.

`bt()`

Set Bluetooth mode

`wifi()`

Set Wi-Fi access point mode. The default ESP address is 192.168.4.1. Indexing of configurable web server controls is shown in image [4](#).

`set_name(name)`

Set ESP name for both Bluetooth and Wi-Fi. Default name is "OPEN-CUBE".

Parameters: `name` (str) – ESP name.

`set_password(password)`

Set ESP Wi-Fi passwords. Password must be at least 8 characters. Default password is "12345678".

Parameters: `password` (str) – ESP password.

bt_read()

Return last received message in Bluetooth mode.

Returns: Received message. If no new message available: None.

Type:

- ASCII mode: str
- Binary mode: bytes

bt_write(*buff*)

Send message in Bluetooth mode.

Parameters: **buff** (buffer: str(ASCII)/bytes(binary)) – Buffer of data to be sent.

bt_set_binary(*header*, *data_size*)

Set Bluetooth mode to binary mode if header is specified and to ASCII mode if header is None.

Parameters: **header** (tuple) – Header containing numbers 0–255, or None.

data_size (int) – Received message size in bytes.

wifi_get_buttons()

Return state of 9 web server buttons in Wi-Fi access point mode.

Returns: Tuple of buttons state..

Type: 9x bool

wifi_get_switches()

Return state of 5 web server switches in Wi-Fi access point mode.

Returns: Tuple of switches state.

Type: 5x bool

wifi_set_indicators(*indicators*)

Set state of 9 web server indicators in Wi-Fi access point mode.

Parameters: **indicators** (tuple) – 5x bool of indicators state.

wifi_set_numbers(*numbers*)

Set state of 6 web server numbers in Wi-Fi access point mode.

Parameters: **indicators** (tuple) – 6x float.

wifi_set_buttons_labels(*labels*)

Set label of 9 web server buttons in Wi-Fi access point mode. String of each button can have a maximum length of 9 characters and an empty string hides the button.

Parameters: **labels** (tuple) – 9x str buttons label.

wifi_set_switches_labels(*labels*)

Set label of 9 web server switches in Wi-Fi access point mode. String of each switch can have a maximum length of 9 characters and an empty string hides the switch.

Parameters: `labels` (tuple) – 5x str switches label.

`wifi_set_indicators_labels(labels)`

Set label of 5 web server indicators in Wi-Fi access point mode. String of each indicator can have a maximum length of 9 characters and an empty string hides the indicator.

Parameters: `labels` (tuple) – 5x str indicators label.

`wifi_set_numbers_labels(labels)`

Set label of 6 web server numbers in Wi-Fi access point mode. String of each number can have a maximum length of 9 characters and an empty string hides the number.

Parameters: `labels` (tuple) – 6x str numbers label.

Example of using communication between the micro controller and ESP32:

```
1 # Import library for working with binary data
2 import struct
3
4 # Send and receive a string message in Bluetooth ASCII mode
5 robot.esp.bt_write("test message")
6 received_message = robot.esp.bt_read()
7
8 # Send and receive a message of 8 bytes in Bluetooth binary mode
9 robot.esp.bt_set_binary((112, 241, 3, 62), 8)
10 # Create and send a message with two numbers of type single (4 bytes
    each)
11 write_message = struct.pack("<ff", 521.9, -11.821)
12 robot.esp.bt_write(write_message)
13 # Receive and decode a message containing two numbers of type single
14 received_message2 = robot.esp.bt_read()
15 (value1, value2) = struct.unpack("<ff", received_message2)
16
17 # Switch ESP to Wi-Fi access point mode
18 robot.esp.wifi()
19 # Set labels of indicators
20 robot.esp.set_indicators_labels(["1", "2", "3", "4", "5"])
21 # Get state of switches
22 switches = robot.esp.get_switches()
```

Code 11: Communication between the micro controller and ESP32.




Figure 4: Indexing of ESP web server elements.

3.9.3 Remote control of the cube

If the cube is in the menu, Bluetooth communication can be used for remote control and running programs.

Control messages:

- `oc l`, `oc r`, `oc u`, `oc d`, `oc o`, `oc ko` – emulation of physical buttons on the cube (left, right, up, down, ok, power),
- `oc fw` – the cube resets to bootloader mode,
- `oc rs` – performs a software reset of the cube,
- `oc run <program name>` – runs the program with the given name,
- `oc ping` – sends back `oc pong`

3.9.4 Wireless program launch

By adding the Open-Cube plugin to the Thonny editor, you can wirelessly upload and run programs:

1. Install the Open-Cube Thonny plugin.
2. Pair the cube with your computer (see 3.9.1).
3. In the Open-Cube Thonny plugin settings, select the cube's COM port.
4. Press the **OC Run** button to upload and run the program.
5. Use the **OC Stop** button to stop the program if the **Take control** option is selected in the plugin settings. At the same time, you can send messages to the Open-Cube log window using `robot.esp.bt_write()`.

3.9.5 Serial Bluetooth Terminal

For a simple Bluetooth communication from your mobile phone you can use the app [Serial Bluetooth Terminal](https://play.google.com/store/apps/details?id=de.kai_morich.serial_bluetooth_terminal) [https://play.google.com/store/apps/details?id=de.kai_morich.serial_bluetooth_terminal]. This app allows you to send and receive messages from the cube in Bluetooth ASCII mode.

3.9.6 Matlab

To communicate with the cube using Matlab, it is necessary to have the Communications Toolbox installed. This interface uses Bluetooth SPP (Serial Port Profile) and allows you to receive and send ASCII and binary data. When sending ASCII data, the message is terminated with a terminator (LF or CF). In the case of binary data, the message is not terminated with a terminator and both the cube and the Matlab program must know the length of the message in advance in order to interpret messages correctly.

An example of using the interface is described in the following code. For more information on how to use the interface, see the official [Bluetooth Communication documentation](https://www.mathworks.com/help/matlab/bluetooth-communication.html) [<https://www.mathworks.com/help/matlab/bluetooth-communication.html>].

```
1 % Connecting the cube with Matlab
2 cube = bluetooth('OPEN-CUBE')
3 % Set LF (new line) terminator for sending and receiving
  ASCII data
4 configureTerminator(device, 'LF')
5 %%
6 % Send a test message to the cube in Bluetooth ASCII mode. The
  message is automatically terminated by the set terminator
7 writeline(cube, 'test message')
8 % Receiving a message from the cube. The function receives
  data and waits for termination by previously set
  terminator.
9 cube_message = readline(cube)
10 %%
```



```

11 % Send a test message to the cube in Bluetooth binary mode.
    The message is interpreted as a string format and is not
    terminated by a terminator.
12 write(cube, 'test message', 'string')
13 % Receive a message from the cube. The message is 8 bytes
    long and is interpreted as float.
14 cube_message2 = read(cube, 8, 'float')

```

Code 12: Communication with the cube using Matlab.

3.9.7 Simulink

For communication using Simulink it is necessary to have the Instrument Control Toolbox installed. This toolbox provides blocks **Serial Configuration**, **Serial Send** and **Serial Receive** for serial communication. When creating a new model, you need to modify the simulation solver settings and set the serial communication parameters as follows:

1. Click the button in the bottom right corner to set the solver to **Fixed-Step, discrete** and **Fixed-step size** to a value according to the frequency of sending and receiving data (e.g. 0.001). See image 5.
2. Click on the arrow below the **Run** button to enable **Simulation Pacing**. See images 6 and 7.
3. Create the **Serial Configuration** block in the model, in which set the COM port found in 3.9.1 and other parameters according to image 8.

After this configuration it is possible to use the blocks **Serial Send** and **Serial Receive** for sending and receiving data. For additional information on how to use the blocks, see v [official documentation](https://www.mathworks.com/help/instrument/direct-interface-communication-in-simulink.html) [<https://www.mathworks.com/help/instrument/direct-interface-communication-in-simulink.html>].

An example of using serial communication to set the PID constants of a controller running in the cube and display the current PID components is shown in image 9. In this example, the values are sent and received in Bluetooth binary mode, the header for sending and receiving is set, and used data type is single (4 bytes). Messages are received every 0.01 seconds, which is set in the **Serial Send** block in the **Block sample time** cell. Messages are sent every second, which is set in the **Block sample time** cell of the three **Constant** blocks. Set **Fixed-step size** of the solver should be smaller than the **Block sample time**.




Figure 5: Simulink solver configuration.




Figure 6: Location of Simulation pacing configuration in Simulink.




Figure 7: Simulink Simulation Pacing configuration.




Figure 8: Configuration of Serial Configuration block in Simulink.




Figure 9: Example of using serial communication in Simulink.

4 NXT sensors

4.1 Touch sensor

```
class TouchSensor(port)
```

NXT Touch Sensor.

Information about the button state.

Parameters: **port** (**Port**) – The port to which the sensor is connected.

Initialization: `robot.init_sensor(sensor_type=Sensor.NXT_TOUCH, - port=Port).`

Deinitialization: `robot.deinit_sensor(sensor_type=Sensor.NXT_TOUCH, - port=Port).`

Access: `robot.sensors.touch[Port].`

```
pressed()
```

Return button state.

Returns: True if the button is pressed, False if not.

Type: bool

```
1 # Import sensor and port constants
2 from lib.robot_consts import Sensor, Port
3
4 # Initialize NXT Touch Sensor on sensor port 1
5 robot.init_sensor(sensor_type=Sensor.NXT_TOUCH, port=Port.S1)
6
7 # Determine the button state
8 touch_pressed = robot.sensors.touch[Port.S1].pressed()
```

Code 13: NXT Touch Sensor usage.

4.2 Light sensor

```
class LightSensor(port)
```

NXT Ligth Sensor.

Measuring light intensity.

Measurement is possible in two modes – manual, in which the intensity is measured on request, and continuous, in which the intensity is measured periodically and on request the last measured value is returned. The continuous mode also provides non-flashing and flashing modes. In the non-flashing mode, the intensity is measured in the LED state previously set by the user. In the flashing mode, the intensity is measured in both the off and on LED states. Changing the LED state is done automatically and the last measured intensity for both LED states is available to the user on request.

The ADC samples the signal with a period of 1 ms. Light intensity is obtained by measuring the voltage on the sensor. When the LED state changes, this voltage will stabilize in approximately 10 ms.

Parameters: `port` (`Port`) – The port to which the sensor is connected.
Initialization: `robot.init_sensor(sensor_type=Sensor.NXT_LIGHT,port=Port)`
Deinitialization: `robot.deinit_sensor(sensor_type=Sensor.NXT_LIGHT,port=Port)`
Access: `robot.sensors.light[Port]`

`on()`

Turn on sensor LED.

`off()`

Turn off sensor LED.

`toggle()`

Change state of sensor LED.

`intensity(pin_on)`

Measure and return light intensity in manual mode. Return last measured light intensity in continuous mode.

Parameters: `pin_on` (bool) – Selection of the returned measured light intensity. The value does not matter in manual mode and in continuous non-flashing mode. In continuous flashing mode, return the measured intensity when the LED is on for True and when the LED is off for False.

Returns: Measured light intensity. 0 for the highest intensity, 32768 for the lowest.

Type: int (0–32768)

`set_continuous(period_us, wait_us)`

Set sensor to continuous mode.

Parameters: • `period_us` (int) – Time in μs between the start of the analog value conversion and the reading of the converted digital value from the ADC. Recommended minimum value is 1100.

• `wait_us` (int) – Waiting time in μs before starting a measurement after LED state change. Recommended minimum value is 10000.

`stop_continuous()`

Set sensor to manual mode.

`set_switching()`

Set sensor in continuous mode to continuous flashing mode.

`stop_switching()`

Set sensor in continuous mode to continuous non-flashing mode.

```
1 # Import sensor and port constants
2 from lib.robot_consts import Sensor, Port
3
4 # Initialize NXT Light Sensor on sensor port 1
5 robot.init_sensor(sensor_type=Sensor.LIGHT, port=Port.S1)
6
7 # Turn on sensor LED
8 robot.sensors.light[Port.S1].on()
9 # Measure light intensity
10 light_intensity = robot.sensors.light[Port.S1].intensity()
```

Code 14: NXT Light Sensor usage.

4.3 Ultrasonic sensor

`class UltrasonicSensor()`

NXT Ultrasonic Sensor.

Measuring distance of an object from the sensor in the range 0–255 cm with an accuracy of ± 3 cm. The sensor must be connected to the cube port marked I2C, multiple NXT Ultrasonic Sensor type sensors cannot be connected.

Initialization: `robot.init_sensor(sensor_type=Sensor.NXT_ULTRASONIC)`

Deinitialization: `robot.deinit_sensor(sensor_type=Sensor.NXT_ULTRASONIC)`

Access: `robot.sensors.ultra_nxt`

`distance()`

Measure and return distance.

Returns: Distance of the nearest object.

Type: int (0-255)

```
1 # Import sensor constants
2 from lib.robot_consts import Sensor
3
4 # Initialize NXT Ultrasonic Sensor on the I2C port
5 robot.init_sensor(sensor_type=Sensor.NXT_ULTRASONIC)
6 # Measure distance
7 distance = robot.sensors.ultra_nxt.distance()
```

Code 15: NXT Ultrasonic Sensor usage.

4.4 Sound sensor

class SoundSensor(*port*)

NXT Sound Sensor.

Measuring ambient sound intensity.

Parameters: **port** ([Port](#)) – The port to which the sensor is connected.

Initialization: robot.init_sensor(sensor_type=[Sensor.NXT_SOUND](#),port=[Port](#))

Deinitialization: robot.deinit_sensor(sensor_type=[Sensor.NXT_SOUND](#),port=[Port](#))

Access: robot.sensors.sound[[Port](#)]

intensity()

Measure and return sound intensity.

Returns: Sound intensity. 0 for the highest intensity, 32768 for the lowest.

Type: int (0–32768)

```
1 # Import sensor and port constants
2 from lib.robot_consts import Sensor, Port
3
4 # Initialize NXT Sound Sensor on sensor port 1
5 robot.init_sensor(sensor_type=Sensor.NXT_SOUND, port=Port.S1)
6
7 # Measure sound intensity
8 sound_intensity = robot.sensors.sound[Port.S1].intensity()
```

Code 16: NXT Sound Sensor usage.

5 EV3 sensors

5.1 Touch sensor

```
class TouchSensor(port)
```

EV3 Touch Sensor.

Information about the button state.

Parameters: `port` (`Port`) – The port to which the sensor is connected.
Initialization: `robot.init_sensor(sensor_type=Sensor.EV3_TOUCH, - port=Port)`
Deinitialization: `robot.deinit_sensor(sensor_type=Sensor.EV3_TOUCH, - port=Port)`
Access: `robot.sensors.touch[Port].`

```
pressed()
```

Return button state.

Returns: True if the button is pressed, False if not.
Type: bool

```
1 # Import sensor and port constants
2 from lib.robot_consts import Sensor, Port
3
4 # Initialize EV3 Touch Sensor on sensor port 1
5 robot.init_sensor(sensor_type=Sensor.EV3_TOUCH, port=Port.S1)
6
7 # Get button state
8 touch_pressed = robot.sensors.touch[Port.S1].pressed()
```

Code 17: EV3 Touch Sensor usage.

5.2 Color sensor

```
class ColorSensor(port)
```

EV3 Color Sensor.

Measuring light intensity and color detection.

Parameters: `port` (`Port`) – The port to which the sensor is connected.
Initialization: `robot.init_sensor(sensor_type=Sensor.EV3_COLOR)`
Deinitialization: `robot.deinit_sensor(sensor_type=Sensor.EV3_COLOR)`
Access: `robot.sensors.light[Port]`

```
reflection()
```

Return last measured reflected light intensity. Sensor red LED periodically switches on and off. Light intensity is measured when the LED is on, from this value a measurement when the LED is off is subtracted. The resulting

value is adjusted using sensor internal calibration and remapped to the 0-100% interval.

Returns: Reflected light intensity.
Type: int (0-100%)

reflection_raw()

Return last measured reflected light intensity in raw format. Sensor red LED periodically switches on and off. Light intensity is measured when the LED is on, from this value a measurement when the LED is off is subtracted.

Returns: Reflected light intensity.
Type: int

ambient()

Return last measured ambient light intensity. The resulting value is adjusted using sensor internal calibration and remapped to the 0-100% interval.

Returns: Ambient light intensity.
Type: int (0-100%)

rgb_raw()

Return last measured reflected light intensity for red, blue and green LEDs turned on and measured separately.

Returns: Tuple of reflected light intensity (red, green, blue).
Type: (int, int, int)

rgb()

Return last measured reflected light intensity for the red, blue and green LEDs turned on and measured separately. The resulting values are adjusted using Open-Cube calibration and remapped to the 0-100% interval.

Returns: Tuple of reflected light intensity (red, green, blue).
Type: (int, int, int) (0-100%)

hsv()

Return HSV values for the last measured reflected light intensity with the red, blue and green LEDs turned on and measured separately.

Returns: Tuple of HSV.
Type: (hue, saturation, value)

color()

Return a constant of sensor detected color. Color constants can be used [Color](#).

Returns: Detected color constant.
Type: int (1-7 – black, blue, green, yellow, red, white, brown)

```
1 # Import sensor constants
2 from lib.robot_consts import Sensor, Port
3
```

```

4 # Initialize EV3 Color Sensor on sensor port 1
5 robot.init_sensor(sensor_type=Sensor.EV3_COLOR, port=Port.S1)
6
7 # Measure reflected light intensity
8 reflection = robot.sensors.light[Port.S1].reflection()

```

Code 18: EV3 Color Sensor usage.

5.3 Ultrasonic sensor

```
class UltrasonicSensor(port)
```

EV3 Ultrasonic Sensor.

Measuring distance of an object from the sensor in range 0–2550 mm with an accuracy of ± 30 mm.

Parameters: `port` (`Port`) – The port to which the sensor is connected.
Initialization: `robot.init_sensor(sensor_type=Sensor.EV3_ULTRASONIC)`
Deinitialization: `robot.deinit_sensor(sensor_type=Sensor.EV3_ULTRASONIC)`
Access: `robot.sensors.ultrasonic[Port]`

```
distance()
```

Return last measured distance.

Returns: Distance of the nearest object. in mm
Type: int (0-2550)

```
presence()
```

Detect presence of another ultrasonic sensor.

Returns: True if an ultrasonic sensor detected, False otherwise.
Type: bool

```

1 # Import sensor constants
2 from lib.robot_consts import Sensor, Port
3
4 # Initialize EV3 Ultrasonic Sensor on sensor port 1
5 robot.init_sensor(sensor_type=Sensor.EV3_ULTRASONIC, port=Port.S1)
6
7 # Measure distance
8 distance = robot.sensors.ultrasonic[Port.S1].distance()

```

Code 19: EV3 Ultrasonic sensor usage.

5.4 Infrared sensor

```
class InfraredSensor(port)
```

EV3 Infrared Sensor.

Measuring the distance to the nearest surface and control by remote controller.

Parameters: `port` (`Port`) – The port to which the sensor is connected.
Initialization: `robot.init_sensor(sensor_type=Sensor.EV3_INFRARED)`
Deinitialization: `robot.deinit_sensor(sensor_type=Sensor.EV3_INFRARED)`
Access: `robot.sensors.infrared[Port]`

`distance()`

Measure relative distance to the nearest surface. 100% is approximately 70 cm.

Returns: Relative distance to the nearest surface.
Type: `int` (0-100%)

`seeker(channel)`

Detect presence of a remote controller on given channel.

Parameters: `channel` (`int`) – Channel to be checked.
Returns: Tuple of direction (-25 is leftmost, 25 rightmost) and distance (100% is approximately 200 cm, -128 if no driver is found) of the controller.
Type: (`int`, `int`) (-25-25, 0-100%)

```
1 # Import sensor constants
2 from lib.robot_consts import Sensor, Port
3
4 # Initialize EV3 Infrared Sensor on sensor port 1
5 robot.init_sensor(sensor_type=Sensor.EV3_INFRARED, port=Port.S1)
6 # Measure distance
7 distance = robot.sensors.infrared[Port.S1].distance()
```

Code 20: EV3 Infrared Sensor usage.

5.5 Gyroscopic sensor

`class GyroSensor(port)`

EV3 Gyro Sensor.

Measuring angle of rotation and angular velocity in one axis.

Parameters: `port` (`Port`) – The port to which the sensor is connected.
Initialization: `robot.init_sensor(sensor_type=Sensor.EV3_GYRO)`
Deinitialization: `robot.deinit_sensor(sensor_type=Sensor.EV3_GYRO)`
Access: `robot.sensors.gyro[Port]`

`angle()`

Return angle of rotation of the sensor.

Returns: Angle of rotation.
Type: `int` (°)

`speed()`

Return angular velocity of the sensor.

Returns: Angular velocity.

Type: int (°/s)

reset_angle(*angle*)

Reset angle measurement or set a new initial angle value.

Parameters: **angle** (int) – Value that the angle method will return if the sensor does not move. 0 to reset angle.

angle_and_speed()

Return angle of rotation and angular velocity of the sensor.

Returns: Tuple of angle of rotation and angular velocity.

Type: (int, int) (°, °/s)

coarse_speed()

Return angular velocity of the sensor with lower resolution and wider range.

Returns: Angular velocity.

Type: int (°/s)

```
1 # Import sensor constants
2 from lib.robot_consts import Sensor, Port
3
4 # Initialize EV3 Gyro Sensor on sensor port 1
5 robot.init_sensor(sensor_type=Sensor.EV3_GYRO, port=Port.S1)
6
7 # Reset angle of rotation
8 robot.sensors.gyro[Port.S1].reset_angle(0)
9
10 # Measure angle of rotation and angular velocity
11 (angle, speed) = robot.sensors.gyro[Port.S1].angle_and_speed()
```

Code 21: EV3 Gyro Sensor usage.

6 Open-Cube sensors

6.1 Color sensor

```
class ColorSensor(port)
```

Open-Cube RGB optical reflective and color sensor.

Measuring light intensity and color detection.

Parameters: `port` (`Port`) – The port to which the sensor is connected.
Initialization: `robot.init_sensor(sensor_type=Sensor.OC_COLOR)`
Deinitialization: `robot.deinit_sensor(sensor_type=Sensor.OC_COLOR)`
Access: `robot.sensors.light[Port]`

reflection()

Return last measured reflected light intensity. Sensor red LED periodically switches on and off. Light intensity is measured when the LED is on, from this value a measurement when the LED is off is subtracted. The resulting value is adjusted using sensor internal calibration and remapped to the 0-100% interval.

Returns: Reflected light intensity.
Type: int (0-100%)

reflection_raw()

Return last measured reflected light intensity in raw format. Sensor red LED periodically switches on and off and measures light intensity for both LED states.

Returns: Tuple of reflected and reference light intensity.
Type: (int, int)

reflection_raw_green()

Return last measured reflected light intensity in raw format. Sensor green LED periodically switches on and off and measures light intensity for both LED states.

Returns: Tuple of reflected and reference light intensity.
Type: (int, int)

reflection_raw_blue()

Return last measured reflected light intensity in raw format. Sensor blue LED periodically switches on and off and measures light intensity for both LED states.

Returns: Tuple of reflected and reference light intensity.
Type: (int, int)

ambient()

Return last measured ambient light intensity. The resulting value is adjusted using sensor internal calibration and remapped to the 0-100% interval.

Returns: Ambient light intensity.
Type: int (0-100%)

rgb_raw()

Return last measured reflected light intensity for red, blue and green LEDs turned on and measured separately and reference light intensity for all LEDs turned off.

Returns: Tuple of reflected light intensity (red, green, blue) and reference light intensity.
Type: (int, int, int, int)

rgb()

Return last measured reflected light intensity for the red, blue and green LEDs turned on and measured separately. The resulting values are adjusted using Open-Cube calibration and remapped to the 0-100% interval.

Returns: Tuple of reflected light intensity (red, green, blue).
Type: (int, int, int) (0-100%)

hsv()

Return HSV values for the last measured reflected light intensity with the red, blue and green LEDs turned on and measured separately.

Returns: Tuple HSV.
Type: (hue, saturation, value)

color()

Return a constant of sensor detected color. Color constants can be used [Color](#).

Returns: Detected color constant.
Type: int (1-7 – black, blue, green, yellow, red, white, brown)

```
1 # Import sensor constants
2 from lib.robot_consts import Sensor, Port
3
4 # Initialize Open-Cube Color Sensor on sensor port 1
5 robot.init_sensor(sensor_type=Sensor.OC_COLOR, port=Port.S1)
6
7 # Measure reflected light intensity
8 reflection = robot.sensors.light[Port.S1].reflection()
```

Code 22: Open-Cube Color Sensor usage.

6.2 Laser distance sensor

```
class LaserSensor(port)
```

Open-Cube LIDAR distance sensor.

Measuring distance of an object from the sensor in the range 0–4000 mm. The minimum guaranteed measurement distance is 4 cm. If the object is closer than this distance, the sensor will measure an inaccurate value.

Parameters: `port` (`Port`) – The port to which the sensor is connected.
Initialization: `robot.init_sensor(sensor_type=Sensor.OC_LASER)`
Deinitialization: `robot.deinit_sensor(sensor_type=Sensor.OC_LASER)`
Access: `robot.sensors.ultrasonic[Port]`

`distance()`

Return last measured distance.

Returns: Distance of the nearest object.
Type: `int` (0-4000)

`distance_fov()`

Return last measured distance. This mode uses a larger sensor field of view.

Returns: Distance of the nearest object.
Type: `int` (0-4000)

`distance_short()`

Return last measured distance. This mode is more accurate for shorter distances (up to 1300 mm) and strong ambient light.

Returns: Distance of the nearest object.
Type: `int` (0-4000)

`set_led_distance(distance)`

Set threshold distance at which the green LED of the sensor lights up.

Parameters: `distance` (`int`) – Threshold distance in mm.

```
1 # Import sensor constants
2 from lib.robot_consts import Sensor, Port
3
4 # Initialize Open-Cube LIDAR on sensor port 1
5 robot.init_sensor(sensor_type=Sensor.OC_LASER, port=Port.S1)
6
7 # Measure distance
8 distance = robot.sensors.laser[Port.S1].distance()
```

Code 23: Open-Cube LIDAR usage.

6.3 Ultrasonic sensor

`class UltrasonicSensor(port)`

Open-Cube Ultrasonic Sensor.

Measuring distance of an object from the sensor in the range 0–9999 mm.

Parameters: `port` (`Port`) – The port to which the sensor is connected.
Initialization: `robot.init_sensor(sensor_type=Sensor.OC_ULTRASONIC)`
Deinitialization: `robot.deinit_sensor(sensor_type=Sensor.OC_ULTRASONIC)`
Access: `robot.sensors.ultrasonic[Port]`

`distance()`

Return last measured distance.

Returns: Distance of the nearest object.

Type: `int` (0-4000)

`set_led_distance(distance)`

Set threshold distance at which the green LED of the sensor lights up.

Parameters: `distance` (`int`) – Threshold distance in mm.

```
1 # Import sensor constants
2 from lib.robot_consts import Sensor, Port
3
4 # Initialize Open-Cube Ultrasonic Sensor on sensor port 1
5 robot.init_sensor(sensor_type=Sensor.OC_ULTRASONIC, port=Port.S1)
6
7 # Measure distance
8 distance = robot.sensors.ultrasonic[Port.S1].distance()
```

Code 24: Open-Cube Ultrasonic sensor usage.

6.4 AHRS sensor

`class GyroSensor(port)`

Open-Cube AHRS (Attitude and Heading Reference System) Sensor.

Measurement of angular velocity, acceleration and magnetic field intensity in three axes.

Parameters: `port` (`Port`) – The port to which the sensor is connected.

Initialization: `robot.init_sensor(sensor_type=Sensor.OC_GYRO)`

Deinitialization: `robot.deinit_sensor(sensor_type=Sensor.OC_GYRO)`

Access: `robot.sensors.gyro[Port]`

`euler_angles()`

Returns the current sensor orientation in Euler angles calculated from the gyroscope and accelerometer.

Returns: Tuple of Euler angles yaw, pitch, roll.

Type: (yaw: -180–180°, pitch: -90–90°, roll: -180–180°)

`euler_angles_mag()`

Returns the current sensor orientation in Euler angles calculated from the gyroscope, accelerometer and magnetometer.

Returns: Tuple of Euler angles yaw, pitch, roll.
Type: (yaw: -180–180°, pitch: -90–90°, roll: -180–180°)

quaternions()

Returns the current sensor orientation in quaternions calculated from the gyroscope and accelerometer.

Returns: Tuple of quaternions.
Type: (0–1, 0–1, 0–1, 0–1)

raw()

Returns the last measured angular velocity, acceleration and magnetic field intensity in the x, y, z axes.

Returns: Tuple of angular velocity, acceleration and magnetic field intensity in the x, y, z axes.
Type: (g_x: °/s, g_y: °/s, g_z: °/s, a_x: -, a_y: -, a_z: -, m_x: mg, m_y: mg, m_z: mg)

calibrate_gyro()

Initiates gyro offset calibration. The sensor must not move during the entire calibration period.

Returns: 1 if calibration is completed.
Type: int (0/1)

calibrate_mag()

Initiates a hard iron calibration of the magnetometer. Rotate the sensor until the calibration is complete.

Returns: 1 if calibration is completed.
Type: int (0/1)

```
1 # Import sensor constants
2 from lib.robot_consts import Sensor, Port
3
4 # Initialize the OC AHRS sensor on sensor port1
5 robot.init_sensor(sensor_type=Sensor.OC_GYRO, port=Port.S1)
6
7 # Gyroscope calibration
8 calibrated = 0
9 while not calibrated:
10     calibrated = robot.sensors.gyro[Port.S1].calibrate_gyro()
11
12 # Get sensor orientation
13 euler_angles = robot.sensors.gyro[Port.S1].euler_angles()
14 yaw, pitch, roll = euler_angles[0], euler_angles[1], euler_angles[2]
```

Code 25: Open-Cube AHRS sensor usage.

7 Motor

The motors from the NXT and EV3 sets are identical internally, differing only in appearance and plastic construction.

```
class Motor(port)
```

Rotary encoders are located on the motors, which allow detecting the motor rotational position and approximating the speed of rotation.

Provides three modes of control – power, position, speed.

In the power control mode, the user directly sets the desired power on the motor in the range of -100–100%.

In the position control mode, the user selects the desired motor rotational position in °. The control is mediated by a PID controller with adjustable constants.

In the speed control mode, the user selects the desired motor speed of rotation in °/s. The maximum speed when the motor is unloaded is approximately 950 °/s. The control is mediated by a PID controller with adjustable constants.

Parameters: **port** (*Port*) – The port to which the motor is connected.

Initialization: `robot.init_motor(port=Port)`

Deinitialization: `robot.deinit_motor(port=Port)`

Access: `robot.motor[Port]`

Parameters: **port** (*Port*) – The port to which the motor is connected.

```
set_power(power)
```

Set power on the motor.

Parameters: **power** (float) – Desired power on the motor in the range of -100–100%. If a value is entered outside this range, the limit value is set.

```
init_encoder()
```

Initialize encoders with a measurement of the motor position and speed on all motors.

```
deinit_encoder()
```

Deinitialize encoders with a measurement of the motor position and speed on all motors.

```
position()
```

Return motor rotational position.

Returns: Motor rotational position.

Type: angle: °

speed()

Return motor speed o rotation.

Returns: Motor speed o rotation.

Type: angular velocity: °/s

init_regulator()

Initialize motor PID controller.

deinit_regulator()

Deinitialize motor PID controller.

set_regulator_position(*position*)

Set motor to position control mode.

Parameters: **position** (int) – Required motor position in °.

regulator_pos_set_consts(*p, i, d*)

Set PID constants of the position controller. The default values are 0.9, 0.1 and 0.

Parameters:

- **p** (float) – Constant of the proportional component.
- **i** (float) – Constant of the integration component.
- **d** (float) – Constant of the derivative component.

set_regulator_speed(*speed*)

Set motor to speed control mode.

Parameters: **speed** (int) – Required motor speed of rotation in °/s.

regulator_speed_set_consts(*p, i, d*)

Set PID constants of the speed controller. The default values are 0.1, 0.8 and 0.

Parameters:

- **p** (float) – Constant of the proportional component.
- **i** (float) – Constant of the integration component.
- **d** (float) – Constant of the derivative component.

regulator_error()

Return current control error.

Returns: Control error.

Type:

- **position control mode** – position: °
- **speed control mode** – angular velocity: °/s

regulator_power()

Return current control action.

Returns: Control action.

Type: power (-100–100%)

```
1 # Import port constants
2 from lib.robot_consts import Port
3
4 # Initialize motors on motor ports 1 and 2
5 robot.init_motor(Port.M1)
6 robot.init_motor(Port.M2)
7
8 # Set power on the motors to 50%, and 20% in the opposite direction of
  rotation
9 robot.motors[Port.M1].set_power(50)
10 robot.motors[Port.M2].set_power(-20)
11
12 # Initialize motors encoders
13 robot.motors[Port.M1].init_encoder()
14 robot.motors[Port.M2].init_encoder()
15
16 # Measure current position and speed of rotation of motors
17 pos1 = robot.motors[Port.M1].position()
18 pos2 = robot.motors[Port.M2].position()
19 speed1 = robot.motors[Port.M1].speed()
20 speed2 = robot.motors[Port.M2].speed()
```

Code 26: Motor usage.

8 Parameters and constants

Parameters and constants importable from `lib.robot_consts`.

8.1 Sensor

class **Sensor**

Sensor types.

NO_SENSOR

No sensor.

NXT_LIGHT

NXT Light Sensor.

NXT_ULTRA

NXT Ultrasonic Sensro.

NXT_TOUCH

NXT Touch Sensor.

NXT_SOUND

NXT Sound Sensor.

GYRO_ACC

ICM20608-G gyroscope and accelerometer.

EV3_COLOR

EV3 Color Sensor.

EV3_GYRO

EV3 Gyroscopic Sensor.

EV3_INFRARED

EV3 Infrarfed Sensor.

EV3_TOUCH

EV3 Touch Sensor.

EV3_ULTRASONIC

EV3 Ultrasonic Sensor.

OC_LASER

Open-Cube LIDAR.

OC_COLOR

Open-Cube Color Sensor.

OC_ULTRASONIC

Open-Cube Ultrasonic Sensor.

OC_GYRO

Open-Cube AHRS Sensor.

8.2 Port

class Port

Motor and sensor port of the cube.

M1

Motor port 1.

M2

Motor port 2.

M3

Motor port 3.

M4

Motor port 4.

S1

Sensor port 1.

S2

Sensor port 2.

S3

Sensor port 3.

S4

Sensor port 4.

8.3 Button

class Button

Cube buttons.

POWER

LEFT

RIGHT

OK

UP

DOWN

8.4 Light

```
class Light
```

Measured value when the NXT light sensor LED is off and on.

OFF

Measured value when the NXT light sensor LED is off.

ON

Measured value when the NXT light sensor LED is on.

8.5 GyroAcc

```
class GyroAcc
```

Measured value of built-in gyroscope and accelerometer ICM42688 in x, y, z axes and sensor interrupt pin.

AX

Acceleration in the x-axis

AY

Acceleration in the y-axis

AZ

Acceleration in the z-axis

GX

Angular velocity in the x-axis.

GY

Angular velocity in the y-axis.

GZ

Angular velocity in the z-axis.

IRQ_PIN

Pin of the micro controller to which the ICM42688 is connected.

8.6 Color

class **Color**

Colors detected by the EV3 and Open-Cube Color Sensors.

BLACK

BLUE

GREEN

YELLOW

RED

WHITE

BROWN

9 Useful MicroPython functions

9.1 Information printing

```
1 x, y = 64, 128.4096
2 y_string = "y"
3
4 # 1. option - separation by commas
5 # This option is suitable for simple and quick printing
6 # Individual elements are separated by a space when printed
7 print("x =", x, ",", y_string, "=", y)
8 # x = 64, y = 128.4096
9
10 # 2. option - use of f-string
11 # This option allows formatting float numbers
12 # d indicates integer type, s indicates string type and f indicates
   float type
13 # .2 specifies the number of displayed decimal places
14 print(f"x = {x:d}, {y_string:s} = {y:.2f}")
15 # x = 64, y = 128.41
16
17 # The use of f-string is also suitable for the cube display
18 robot.display.fill(0)
19 # first line of the display
20 robot.display.text(f"x = {x:d}", 0, 0, 1)
21 # second line of the display
22 robot.display.text(f"{y_string:s} = {y:.2f}", 0, 10, 1)
23 robot.display.show()
24
25 # Printing without line breaks
26 for i in range(10)
27     print(i, end="")
28 print() # line break at the end
29 # 123456789
```

Code 27: Printing information.

9.2 Random number generation

Example of random number generation.

- [MicroPython random library documentation](https://docs.micropython.org/en/latest/library/random.html) [<https://docs.micropython.org/en/latest/library/random.html>]

```
1 # Import functions from the random library
2 from random import random, randint
3
4 random() # Random float number in interval [0.0, 1.0)
5
6 a, b = 0, 100
7 randint(a, b) # Random integer in the interval [a, b]
```

Code 28: Random library usage.

9.3 Time

Example of functions for putting the program to sleep, timing, and periodic function calls using the timer.

- [MicroPython time library documentation](https://docs.micropython.org/en/latest/library/time.html) [<https://docs.micropython.org/en/latest/library/time.html>]
- [MicroPython documentation of Timer class](https://docs.micropython.org/en/latest/library/machine.Timer.html) [<https://docs.micropython.org/en/latest/library/machine.Timer.html>]

```
1 # Import functions from the sleep library
2 from time import sleep, sleep_ms, sleep_us, ticks_us, ticks_diff
3
4 start_time = ticks_us() # Get start time in microseconds
5
6 sleep(1)      # Sleep for 1 second
7 sleep_ms(2)   # Sleep for 2 milliseconds
8 sleep_us(3)   # Sleep for 3 microseconds
9
10 end_time = ticks_us() # Get end time in microseconds
11 print(ticks_diff(end_time, start_time), "us") # 1002003 us
```

Code 29: Time library usage.

```
1 # Import class Timer
2 from machine import Timer
3
4 counter = 0
5
6 # Definition of callback function for timers
7 def my_callback(t):
8     global counter
9     counter += 1
10    print(counter)
11
12 # Initializing a timer that calls the callback function periodically
13 #   with a frequency of 100 Hz
14 # -1 indicates a virtual timer (the rp2040 microcontroller does not
15 #   allow the use of hardware timers)
16 timer1 = Timer(-1)
17 timer1.init(mode=Timer.PERIODIC, freq=100, callback=my_callback)
18
19 # Initializing a timer that calls the callback function only once after
20 #   1000 ms
21 timer2 = Timer(-1)
22 timer2.init(mode=Timer.ONE_SHOT, period=1000, callback=my_callback)
23
24 # Turn off the periodic timer
25 timer1.deinit()
```

Code 30: Timer class usage.

9.4 Binary data manipulation

These functions are useful when working with binary data e.g. when communicating wirelessly via [ESP32](#).

- [MicroPython struct library documentation](https://docs.micropython.org/en/latest/library/struct.html) [<https://docs.micropython.org/en/latest/library/struct.html>]

```
1 # Import struct library
2 import struct
3
4 # Creating binary data from three numbers. The format of the numbers is
   determined by the string of the first function argument. The string
   format is described in detail in the struct library documentation.
5 # In this case, the first number is stored as int (4 bytes), the second
   as float (4 bytes) and the third as double (8 bytes).
6 binary_data = struct.pack("@ifd", 12, 1.234, 5)
7
8 # Backward Conversion of binary data
9 values = struct.unpack("@ifd", binary_data)
10
11 # Compute the memory size in bytes needed to store binary data
12 byte_size = struct.calcsize("@ifd")
13 print(byte_size) # 16
```

Code 31: Struct library usage.

9.5 Multi-core programming

The rp2040 micro controller has 2 cores, only one core is used by default. The use of a second core is possible, but is currently only experimental in MicroPython.

- [Python _thread library documentation](https://docs.python.org/3.5/library/_thread.html) [https://docs.python.org/3.5/library/_thread.html]

```
1 # Import library _thread a function sleep
2 import _thread
3 from time import sleep
4
5 lock = _thread.allocate_lock()
6 counter = 0
7
8 # Second core function definition
9 def core2():
10     global counter
11     lock.acquire() # Lock for working with shared data
12     counter += 1
13     lock.release() # Release
14     _thread.exit() # Termination of second core
15
16 # Second core activation
17 _thread.start_new_thread(core2, ())
18
19 lock.acquire() # Lock for working with shared data
20 print(counter)
21 lock.release() # Release
```

Code 32: _thread library usage.

10 Used Python terms

Data types:

- **int** (integer) – (12, -51),
- **float** – decimal number (120.32, -0.1248),
- **bool** – logical value (True, False),
- **str** (string) – text string ("abc", "Open-Cube").

Data structures:

- **list** – sequence of data that can contain elements of different data types. Individual elements can be changed, added and removed. It is written in square brackets and the elements are separated by commas. [1, "Open-Cube", True, 0.23]
- **tuple** – A sequence of data that can contain elements of different data types. Individual elements cannot be changed, added or removed. It is written in round brackets and the elements are separated by commas. (1, "Open-Cube", True, 0.23)

Key words:

- **None** – no value (sensor not working, failed to measure value, etc.).